

Chapter 177

Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design

Introduction

Senn (2002) defines a *cross-over* design as one in which each subject receives all treatments and the objective is to study differences among the treatments. The name *cross-over* comes from the most common case in which there are only two treatments. In this case, each subject *crosses over* from one treatment to the other. It is assumed that there is a *washout* period between treatments during which the response returns back to its baseline value. If this does not occur, there is said to be a *carry-over* effect.

A 2×2 cross-over design contains two *sequences* (treatment orderings) and two time periods (occasions). One sequence receives treatment A followed by treatment B. The other sequence receives B and then A. The design includes a washout period between responses to make certain that the effects of the first drug do not carry over to the second. Thus, the groups in this design are defined by the sequence in which the drugs are administered, not by the treatments they receive. Indeed, higher-order cross-over designs have been used in which the same treatment is used at both occasions.

Cross-over designs are employed because, if the no-carryover assumption is met, treatment differences are measured within a subject rather than between subjects—making a more precise measurement. Examples of the situations that might use a cross-over design are the comparison of anti-inflammatory drugs in arthritis and the comparison of hypotensive agents in essential hypertension. In both cases, symptoms are expected to return to their usual baseline level shortly after the treatment is stopped.

The sample size calculations in the procedure are based on the formulas presented in Chow, Shao, Wang, & Lohknygina (2018).

Advantages of Cross-Over Designs

A comparison of treatments on the same subject is expected to be more precise. The increased precision often translates into a smaller sample size. Also, patient enrollment into the study may be easier because each patient will receive both treatments. Finally, it is often more difficult to obtain a subject than to obtain a measurement.

Disadvantages of Cross-Over Designs

The statistical analysis of a cross-over experiment is more complex than a parallel-group experiment and requires additional assumptions. It may be difficult to separate the treatment effect from the period effect, the carry-over effect of the previous treatment, and the interaction between period and treatment.

The design cannot be used when the treatment (or the measurement of the response) alters the subject permanently. Hence, it should not be used to compare treatments that are intended to provide a cure.

Because subjects must be measured at least twice, it is often more difficult to keep patients enrolled in the study. It is arguably simpler to measure a subject once than to obtain their measurement twice. This is particularly true when the measurement process is painful, uncomfortable, embarrassing, or time consuming.

Technical Details

The 2×2 crossover design may be described as follows. Randomly assign the subjects to one of two sequence groups so that there are n_1 subjects in sequence one and n_2 subjects in sequence two. In order to achieve design balance, the sample sizes n_1 and n_2 are assumed to be equal so that $n_1 = n_2 = N/2$.

Sequence one is given treatment A followed by treatment B. Sequence two is given treatment B followed by treatment A.

The design can be analyzed using a simple z -test if we ignore period and sequence effects or using a more complex random effects logistic regression model that adjusts for period and sequence effects. The sample size calculations herein ignore period and sequence effects. Julious (2010) suggests on page 175 that the bias due to ignoring period effects if a period-adjusted analysis is planned is not great and that sample size calculations that ignore period effects are adequate.

Cross-Over Design

The discussions that follow summarize the results in Chow, Shao, Wang, & Lokhnygina (2018). Consider a 2×2 cross-over design and let x_{ijk} represent the binary response (0 or 1) from the j^{th} subject ($j = 1, \dots, n_i$) in the i^{th} sequence ($i = 1, 2$) given the k^{th} treatment ($k = 1, 2$). Here we assume that the sample sizes are equal in both sequences such that $n_1 = n_2 = n$. If replicates are taken from each subject (as in a 2×2 m replicated cross-over design) then $x_{ijk} = \bar{x}_{ijk} = \frac{1}{m} (\sum_{l=1}^m x_{ijkl})$, where x_{ijkl} represents the l^{th} binary response replicate ($l = 1, \dots, m$) from the j^{th} subject ($j = 1, \dots, n_i$) in the i^{th} sequence ($i = 1, 2$) given the k^{th} treatment ($k = 1, 2$). The observations taken from the same subject may be correlated with one another. If we assume no sequence and period effects, then we can state that $P(x_{ijk} = 1) = P_k$. Further define the paired differences of treatment – control for each subject within each sequence as

$$\begin{aligned} d_{ij} &= x_{ijT} - x_{ijC} \\ &= x_{ij1} - x_{ij2} \end{aligned}$$

and the overall treatment – control difference as

$$\begin{aligned} \delta &= P_T - P_C \\ &= P_1 - P_2. \end{aligned}$$

Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design

The overall difference can be estimated as

$$\hat{\delta} = \frac{1}{2n} \sum_{i=1}^2 \sum_{j=1}^n d_{ij}.$$

The estimated difference is asymptotically normally distributed with variance σ_d^2 , which can be estimated as

$$\hat{\sigma}_d^2 = \frac{1}{2(n-1)} \sum_{i=1}^2 \sum_{j=1}^n (d_{ij} - \bar{d}_i)^2,$$

where

$$\bar{d}_i = \frac{1}{n} \sum_{j=1}^n d_{ij}.$$

The standard deviation, then, is

$$SD = \sigma_d = \sqrt{\sigma_d^2}$$

with estimate

$$\widehat{SD} = \hat{\sigma}_d = \sqrt{\hat{\sigma}_d^2}.$$

Equivalence Test Statistics

The null and alternative hypotheses for an equivalence test are

$$H_0: P_T - P_C \leq D_{0L} \text{ or } P_T - P_C \geq D_{0U} \quad \text{vs} \quad H_A: D_{0L} < P_T - P_C < D_{0U}$$

or equivalently

$$H_0: \delta \leq D_{0L} \text{ or } \delta \geq D_{0U} \quad \text{vs} \quad H_A: D_{0L} < \delta < D_{0U}$$

where D_{0L} and D_{0U} are the lower and upper equivalence bounds, respectively (i.e. the smallest and largest differences ($P_T - P_C$) for which the treatment and control will be considered equivalent).

The power and sample size calculations are based on the two one-sided test (TOST) statistics

$$Z_L = \frac{\hat{\delta} - D_{0L}}{\frac{\hat{\sigma}_d}{\sqrt{2n}}} \quad \text{and} \quad Z_U = \frac{\hat{\delta} - D_{0U}}{\frac{\hat{\sigma}_d}{\sqrt{2n}}}$$

which are each asymptotically distributed as standard normal under the null hypothesis. The null hypothesis is rejected in favor of the alternative at level α using the TOST procedure if

$$Z_L > Z_{1-\alpha} \quad \text{and} \quad Z_U < Z_\alpha$$

where $Z_{1-\alpha}$ is the upper $1 - \alpha$ percentile and Z_α is the lower α percentile of the standard normal distribution.

Equivalence Power Calculation

Derived from Chow, Shao, Wang, & Lokhnygina (2018) page 85, the power for an equivalence test of $H_0: \delta \leq D_{0L}$ or $\delta \geq D_{0U}$ versus $H_A: D_{0L} < \delta < D_{0U}$ is given as

$$\Phi\left(\frac{D_{0U} - \delta_1}{\frac{\sigma_d}{\sqrt{2n}}} - Z_{1-\alpha}\right) - \Phi\left(\frac{D_{0L} - \delta_1}{\frac{\sigma_d}{\sqrt{2n}}} + Z_{1-\alpha}\right)$$

where $\Phi()$ is the standard normal distribution function, δ_1 is the actual value of the difference under the alternative hypothesis, and $Z_{1-\alpha}$ is the upper $1 - \alpha$ percentile of the standard normal distribution. The sample size is determined using a binary search of possible values for n .

Procedure Options

This section describes the options that are specific to this procedure. These are located on the Design tab. For more information about the options of other tabs, go to the Procedure Window chapter.

Design Tab

The Design tab contains most of the parameters and options that you will be concerned with.

Solve For

Solve For

This option specifies the parameter to be calculated from the values of the other parameters. Under most conditions, you would select either *Power* or *Sample Size*.

Select *Sample Size* when you want to determine the sample size needed to achieve a given power and alpha level.

Select *Power* when you want to calculate the power of an experiment that has already been run.

Select *Effect Size (DI)* when you want to calculate the minimum effect size that can be detected for a particular design.

Power and Alpha

Power

This option specifies one or more values for power. Power is the probability of rejecting a false null hypothesis, and is equal to one minus Beta. Beta is the probability of a type-II error, which occurs when a false null hypothesis is not rejected. In this procedure, a type-II error occurs when you fail to reject the null hypothesis of equal means when in fact the means are different.

Values must be between zero and one. Historically, the value of 0.80 (Beta = 0.20) was used for power. Now, 0.90 (Beta = 0.10) is also commonly used.

A single value may be entered here or a range of values such as *0.8 to 0.95 by 0.05* may be entered.

Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design

Alpha

This option specifies one or more values for the probability of a type-I error. A type-I error occurs when a true null hypothesis is rejected. In this procedure, a type-I error occurs when you reject the null hypothesis of equal means when in fact the means are equal.

Values must be between zero and one. Historically, the value of 0.05 has been used for alpha. This means that about one test in twenty will falsely reject the null hypothesis. You should pick a value for alpha that represents the risk of a type-I error you are willing to take in your experimental situation.

You may enter a range of values such as *0.01 0.05 0.10* or *0.01 to 0.10 by 0.01*.

Sample Size

n (Sample Size per Sequence)

This is the sample size of each sequence or group (AB and BA) in the cross-over design. The individual sequence sample sizes are assumed to be equal such that the total sample size is equal to $N = 2n$.

You can enter a single value such as *50* or a list of values using the syntax *50 100 150 200 250* or *50 to 250 by 50*.

Effect Size – Equivalence Differences

D0.U (Upper Equivalence Difference)

Specify the upper equivalence bound for the difference. This value along with the lower equivalence difference (D0.L) is used to setup the hypothesis test. This value represents the largest difference (Pt - Pc) for which the treatment and control will be considered equivalent.

You can enter a single value such as *0.5* or a series of values such as *0.5 0.6 0.7* or *0.5 to 0.7 by 0.1* in the range $0 < D0.U < 1$ and $D0.U > D1$.

D0.L (Lower Equivalence Difference)

Specify the lower equivalence bound for the difference. This value along with the upper equivalence difference (D0.U) is used to setup the hypothesis test. This value represents the smallest difference (Pt - Pc) for which the treatment and control will be considered equivalent.

For symmetric bounds, enter $-D0.U$. This is the default. You can also enter a single value such as -0.5 or a series of values such as $-0.7 -0.6 -0.5$ or $-0.7 to -0.5 by 0.1$ in the range $-1 < D0.L < 0$ and $D0.L < D1$. Note that if you enter values for D0.L other than $-D0.U$, they are used in pairs with the values of D0.U. Thus, the first values of D0.U and D0.L are used, then the second values of each are used, and so on.

Effect Size – Actual Difference

D1 (Actual Difference)

Enter a value for the actual difference (Pt - Pc) at which power is calculated.

You can enter a single value such as *0* or a series of values such as *0 0.1 0.2* or *0 to 0.2 by 0.1* in the range $-1 < D1 < 1$ and $D0.L < D1 < D0.U$.

Effect Size – Standard Deviation of Paired Differences

Standard Deviation (SD)

Enter a value for the standard deviation of the paired differences, SD.

Estimating SD using Previous 2x2 Cross-Over Data

The standard deviation may be estimated using cell counts from a previous 2x2 cross-over study with n subjects per sequence as described on pages 82 and 83 of Chow, Shao, Wang, & Lokhnygina (2018).

Assume x_{ij1} is the binary treatment response of the j th subject ($j = 1$ to n) in the i th sequence ($i = 1, 2$), and x_{ij2} is the binary control or reference response of the j th subject ($j = 1$ to n) in the i th sequence ($i = 1, 2$). Note that the number of subjects in sequence 1 is equal to the number of subjects in sequence 2 such that $n_1 = n_2 = n$.

Define

$$d_{ij} = x_{ij1} - x_{ij2}$$

$$\bar{d}_{i} = (1/n)\sum_j d_{ij}$$

The formula for SD is then

$$SD = \sqrt{[(\sum_i \sum_j (d_{ij} - \bar{d}_i)^2) / (2(n-1))]}.$$

Example 1 – Power Analysis

Suppose you want to consider the power of an equivalence test of the hypotheses $H_0: \delta \leq -0.2$ or $\delta \geq 0.2$ versus $H_A: -0.2 < \delta < 0.2$ in a balanced cross-over design with a binary endpoint where the test is computed based on the difference for sequence sample sizes between 50 and 200. Let's assume that the actual difference is 0 and the estimated standard deviation of the paired differences is 1. The significance level is 0.05.

Setup

This section presents the values of each of the parameters needed to run this example. First, from the PASS Home window, load the **Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design** procedure window by expanding **Proportions**, then **Cross-Over (2x2) Design**, then clicking on **Equivalence**, and then clicking on **Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design**. You may then make the appropriate entries as listed below, or open **Example 1** by going to the **File** menu and choosing **Open Example Template**.

<u>Option</u>	<u>Value</u>
Design Tab	
Solve For	Power
Alpha.....	0.05
n (Sample Size per Sequence).....	50 to 200 by 50
D0.U (Upper Equivalence Difference)	0.2
D0.L (Lower Equivalence Difference).....	-D0.U
D1 (Actual Difference)	0
Standard Deviation (SD).....	1

Annotated Output

Click the Calculate button to perform the calculations and generate the following output.

Numeric Results

Numeric Results for an Equivalence Test

$H_0: Pt - Pc \leq D0.L$ or $Pt - Pc \geq D0.U$ vs. $H_1: D0.L < Pt - Pc < D0.U$

	Sequence Sample Size	Total Sample Size	Lower Equiv. Difference	Upper Equiv. Difference	Actual Difference	Standard Deviation	Alpha
Power	n	N	D0.L	D0.U	D1	SD	
0.27752	50	100	-0.200	0.200	0.000	1.000	0.050
0.76342	100	200	-0.200	0.200	0.000	1.000	0.050
0.93113	150	300	-0.200	0.200	0.000	1.000	0.050
0.98148	200	400	-0.200	0.200	0.000	1.000	0.050

References

Chow, S.C., Shao, J., Wang, H., and Lohknygina, Y. 2018. Sample Size Calculations in Clinical Research, Third Edition. Chapman & Hall/CRC. Boca Raton, Florida.

Report Definitions

Power is the probability of rejecting a false null hypothesis. It should be close to one.

n is the sample size in each sequence (or group).

N is the total sample size from both sequences. The sample is divided equally among sequences.

D0.L is the lower equivalence difference used to specify the hypothesis test.

D0.U is the upper equivalence difference used to specify the hypothesis test.

D1 is the actual difference at which power is calculated.

SD is the standard deviation of paired differences. This is estimated from a previous study.

Alpha is the probability of rejecting a true null hypothesis. It should be small.

Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design

Summary Statements

For a 2x2 cross-over design, a sample size of 50 in each sequence for a total of 100 achieves 27.752% power to detect a difference of 0.000 using an equivalence test with lower and upper equivalence bounds of -0.200 and 0.200, respectively, with a significance level of 0.050 when the standard deviation of paired differences is 1.000.


Dropout-Inflated Sample Size

Dropout Rate	Sample Size		Dropout-Inflated Enrollment Sample Size		Expected Number of Dropouts	
	n	N	n'	N'	d	D
20%	50	100	63	126	13	26
20%	100	200	125	250	25	50
20%	150	300	188	376	38	76
20%	200	400	250	500	50	100

Definitions

Dropout Rate (DR) is the percentage of subjects (or items) that are expected to be lost at random during the course of the study and for whom no response data will be collected (i.e. will be treated as "missing"). n and N are the evaluable group and total sample sizes, respectively, at which power is computed (as entered by the user). If n subjects from each group are evaluated out of the n' subjects that are enrolled in the study, the design will achieve the stated power. $N = 2n$. n' and N' are the number of subjects that should be enrolled in the study in order to end up with n and N evaluable subjects, based on the assumed dropout rate. n' is calculated by inflating n using the formula $n' = n / (1 - DR)$, with n' always rounded up. (See Julious, S.A. (2010) pages 52-53, or Chow, S.C., Shao, J., and Wang, H. (2008) pages 39-40.). $N' = 2n'$. d and D are the expected number of group and total dropouts, respectively. $d = n' - n$ and $D = 2d$.

Charts Section



This report shows the values of each of the parameters, one scenario per row. This plot shows the relationship between sample size and power. We see that a sample size of just over 100 per sequence is required for 80% power.

Example 2 – Calculating Sample Size when Estimating the Standard Deviation from a Previous Study

This example demonstrates how to calculate the sample size when estimating the standard deviation of the paired differences from data in a previous study using the method in Chow, Shao, Wang, & Lokhnygina (2018) on pages 82 and 83. In this example we'll find the sample size required to detect a difference of 0 with 90% power in a test of the hypotheses $H_0: \delta \leq -0.2$ or $\delta \geq 0.2$ versus $H_A: -0.2 < \delta < 0.2$ at a significance level of 0.05, with the standard deviation estimated using cell counts from a previous 2x2 cross-over study with equal sample size per sequence.

Assume that the following results were previously obtained from 280 subjects in a simple 2x2 cross-over trial comparing two inhalation devices, A and B. These results are similar to Table 3.2 of Lui (2016) on page 36 with a slight adjustment to sequence 1 that makes the sample sizes equal per sequence.

SEQUENCE 1 (Control (A) → Treatment (B))					SEQUENCE 2 (Treatment (B) → Control (A))				
		Period 2 (B)					Period 2 (A)		
		Yes	No	Total			Yes	No	Total
Period 1 (A)	Yes	27	41	67	Period 1 (B)	Yes	38	16	54
	No	15	57	72		No	32	54	86
Total		42	98	140	Total		70	70	140

The paired differences of treatment – control for each subject within each sequence are

$$\begin{aligned} d_{ij} &= x_{ijT} - x_{ijC} \\ &= x_{ijB} - x_{ijA} \end{aligned}$$

If x_{ijk} is a binary variable, then d_{ij} can take on the values 0, 1, and -1. If we summarize the results in sequence 1, then there are 15 subjects with $d_{ij} = 1$ (B = “Yes”, A = “No”), 41 subjects with $d_{ij} = -1$ (B = “No”, A = “Yes”), and $27 + 57 = 84$ subjects with $d_{ij} = 0$ (B = “Yes”, A = “Yes” or B = “No”, A = “No”). The average paired difference, then, for sequence 1 is

$$\begin{aligned} \bar{d}_1 &= \frac{1}{n} \sum_{j=1}^n d_{1j} \\ &= \frac{15(1) + 41(-1) + 84(0)}{140} \\ &= \frac{15 - 41}{140} \\ &= -0.1857. \end{aligned}$$

Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design

Similarly, the average paired difference from sequence 2 is

$$\begin{aligned}\bar{d}_2 &= \frac{1}{n} \sum_{j=1}^n d_{2j} \\ &= \frac{16(1) + 32(-1) + 92(0)}{140} \\ &= \frac{16 - 32}{140} \\ &= -0.1143.\end{aligned}$$

The estimated overall treatment – control difference is

$$\begin{aligned}\hat{\delta} &= \frac{1}{2n} \sum_{i=1}^2 \sum_{j=1}^n d_{ij} \\ &= \frac{\bar{d}_1 + \bar{d}_2}{2} \\ &= \frac{-0.1857 - 0.1143}{2} \\ &= -0.15.\end{aligned}$$

The estimated variance of paired differences, then, is

$$\begin{aligned}\hat{\sigma}_d^2 &= \frac{1}{2(n-1)} \sum_{i=1}^2 \sum_{j=1}^n (d_{ij} - \bar{d}_i)^2 \\ &= \frac{15(1 + 0.1857)^2 + 41(-1 + 0.1857)^2 + 84(0 + 0.1857)^2 + 16(1 + 0.1143)^2 + 32(-1 + 0.1143)^2 + 92(0 + 0.1143)^2}{2(139)} \\ &= 0.3502\end{aligned}$$

with estimated standard deviation

$$\begin{aligned}\widehat{SD} &= \hat{\sigma}_d \\ &= \sqrt{\hat{\sigma}_d^2} \\ &= \sqrt{0.3502} \\ &= 0.5917.\end{aligned}$$

Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design

Setup

This section presents the values of each of the parameters needed to run this example. First, from the PASS Home window, load the **Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design** procedure window by expanding **Proportions**, then **Cross-Over (2x2) Design**, then clicking on **Equivalence**, and then clicking on **Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design**. You may then make the appropriate entries as listed below, or open **Example 2** by going to the **File** menu and choosing **Open Example Template**.

<u>Option</u>	<u>Value</u>
Design Tab	
Solve For	Sample Size
Power.....	0.90
Alpha.....	0.05
D0.U (Upper Equivalence Difference)	0.2
D0.L (Lower Equivalence Difference).....	-D0.U
D1 (Actual Difference)	0
Standard Deviation (SD).....	0.5917

Output

Click the Calculate button to perform the calculations and generate the following output.

Numeric Results

Numeric Results for an Equivalence Test							
H0: $P_t - P_c \leq D0.L$ or $P_t - P_c \geq D0.U$ vs. H1: $D0.L < P_t - P_c < D0.U$							
Power	Sequence Sample Size n	Total Sample Size N	Lower Equiv. Difference D0.L	Upper Equiv. Difference D0.U	Actual Difference D1	Standard Deviation SD	Alpha
0.90447	48	96	-0.200	0.200	0.000	0.592	0.050

This report indicates that the required sample size for 90% power is 48 per sequence for a total of 96.

Example 3 – Calculating Sample Size (Validation using Chow, Shao, Wang, & Lokhnygina (2018))

On page 86, Chow, Shao, Wang, & Lokhnygina (2018) presents an example of finding the sample size required to detect a difference of 0 in an equivalence test with a margin of 0.2 with 80% power at a significance level of 0.05 when the standard deviation of paired differences is 0.5. They compute the required sample size to be 27 per sequence.

Setup

This section presents the values of each of the parameters needed to run this example. First, from the PASS Home window, load the **Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design** procedure window by expanding **Proportions**, then **Cross-Over (2x2) Design**, then clicking on **Equivalence**, and then clicking on **Equivalence Tests for the Difference of Two Proportions in a 2x2 Cross-Over Design**. You may then make the appropriate entries as listed below, or open **Example 3** by going to the **File** menu and choosing **Open Example Template**.

<u>Option</u>	<u>Value</u>
Design Tab	
Solve For	Sample Size
Power.....	0.8
Alpha.....	0.05
D0.U (Upper Equivalence Difference)	0.2
D0.L (Lower Equivalence Difference).....	-D0.U
D1 (Actual Difference)	0
Standard Deviation (SD).....	0.5

Output

Click the Calculate button to perform the calculations and generate the following output.

Numeric Results

Numeric Results for an Equivalence Test								
H0: $P_t - P_c \leq D0.L$ or $P_t - P_c \geq D0.U$ vs. H1: $D0.L < P_t - P_c < D0.U$								
	Sequence Sample Size	Total Sample Size	Lower Equiv. Difference	Upper Equiv. Difference	Actual Difference	Standard Deviation		
	n	N	D0.L	D0.U	D1	SD	Alpha	
Power	0.80452	27	54	-0.200	0.200	0.000	0.500	0.050

The result from **PASS** matches the result in Chow, Shao, Wang, & Lokhnygina (2018) exactly.